


# DYNAMICS DIMENSIONS

Dynamics Dimensions allows users to set up Business Central so that when a new record is created, a Dimension Value is automatically created and set for the table.

This means that, for example, Business Central could be set up by the user so that each time a new Customer is created, a new Dimension Value based on the Customer No. would also be created.

## 1. Setup

Dynamics Dimensions has two permission sets; Dynamics Dimensions-View and Dynamics Dimensions-Edit. The Dynamics Dimensions-View is also added to the D365 Basic permission set so that it will work for all users with that permission set.



← Permission Sets

× One or more System permission sets that you have copied to create your own have changed. You may want to review the changes.

🔍 Dynamics Dim ✕ | + New | 📄 Edit List | 🗑️ Delete | 🛡️ Permissions | 📄 Copy Permission Set...

🔍 Permission Set ↑	🔍 Name	🔍 Type ↑	🔍 Extension Name
→ DC1DDI DYNDIM-E...	Dynamics Dimensions-Edit	System	AL.DynamicsDimension
DC1DDI DYNDIM-...	Dynamics Dimensions-View	System	AL.DynamicsDimension


## 2. Features

Dynamics Dimensions adds the following features to Business Central:

- Automatically create a Dimension Value and set it against a record.
- Create Dimension Values for existing records.

## 3. Setup

To turn on the Dynamics Dimensions functionality, please go to the Dynamic Feature Management (using the Business Central Search) and check the Enabled checkbox.



← Dynamics Feature Management

✓ Saved | 📄 | 🗑️ | ↻

🔍 Dimen ✕ | 📄 Edit List | ⚙️ Related Setup | Related ▾ | Automate ▾ | Fewer options | 📄 | 🔍 | ☰ | 🔴

🔍 Feature ↑	Enabled	🔍 Extension Name	🔍 Expiry Warning Date	🔍 Expiry Date
→ Dynamics Dimensions	<input type="checkbox"/>	AL.DynamicsDimension		

**Dynamics Feature Description**

Dynamics Dimensions allows users to default dimensions for tables with no coding required.

From this page, you can also click on the Related Setup action here to open the Dynamics Dimensions Setup page (can also be opened using the Business Central Search).

← Dynamics Dimensions Setup ✓ Saved   

    **Edit List** | Actions ▾ Automate ▾ Fewer options   

Table	Dimension Code	Field
Salesperson/Purchaser		
Location		
G/L Account		
Customer	CUSTOMER	Name
Vendor		
Item		
Sales Header		

The records in this page are automatically created when the page is opened. Only tables where the last field in the Primary Key is a Code field of length 20 or less are included.

On this page, there are the following fields:

- Table – Specifies the table.
- Dimension Code – Specifies the Dimension Code to be Set.
- Field – Specifies the field to be used for the Dimension Value. If blank then the value in the Code (last field in the primary key) field is used.

There is also an Action called Update Existing Records. When run, or when the Dimension Code or Field value is updated, the system will update existing records with the dimension.

For example, on a Cronus system, if you set the Dimension Code on the Customer record to Customer, and the Field to Name, as shown in the screenshot above, then a Dimension Value will be created with a Code of the Customer ID e.g. 10000, and a value of Adatum Corporation

← Customer 10000 ✓ Saved  

**Default Dimensions**     + New **Edit List**  Delete | More options   

Dimension Code ↑	Dimension Value Code	Dimension Value Name	Value Posting	Allowed Values Filter
AREA	40	Europe North (Non EU)	Code Mand...	
→ CUSTOMER	10000	Adatum Corporation		-
CUSTOMERG...	SMALL	Small Business		
DEPARTMENT	SALES	Sales		